

Oracle® Database

Client Quick Installation Guide

10g Release 2 (10.2) for hp-ux PA-RISC (64-Bit)

B19071-01

August 2005

ORACLE®

Copyright © 2005, Oracle. All rights reserved.

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software—Restricted Rights (June 1987). Oracle Corporation, 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

Oracle, JD Edwards, PeopleSoft, and Retek are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

This guide describes how to quickly install Oracle Database Client on HP-UX systems. It includes information about the following:

1. [Reviewing Information About this Guide](#)
2. [Logging In to the System as root](#)
3. [Checking the Hardware Requirements](#)
4. [Checking the Software Requirements](#)
5. [Creating Required Operating System Group and User](#)
6. [Creating an Oracle Base Directory](#)
7. [Configuring the oracle User's Environment](#)
8. [Mounting the Product Disc](#)
9. [Installing Oracle Database Client](#)
10. [What to Do Next?](#)
11. [Documentation Accessibility](#)

Reviewing Information About this Guide

Note: This guide describes how to install Oracle Client on a system that does not have any Oracle software installed on it. If there is an existing Oracle software installation on this system, then refer to *Oracle Database Client Installation Guide for hp-ux PA-RISC (64-Bit)* for more detailed installation instructions.

This guide describes how to complete a default installation of Oracle Database Client on a system that does not have any Oracle software installed on it. It describes how to install one of the following installation types:

- **Administrator:** Enables applications to connect to an Oracle Database instance on the local system or on a remote system. It also provides tools that enable you to administer Oracle Database.
- **Runtime:** Enables applications to connect to an Oracle Database instance on the local system or on a remote system.

- **Instant Client:** Enables you to install only the shared libraries required by Oracle Call Interface (OCI), Oracle C++ Call Interface (OCCI), Pro*C, or Java database connectivity (JDBC) OCI applications. This installation type requires much less disk space as compared to the other Oracle Database Client installation types.

See Also: Oracle Call Interface Programmer's Guide for more information about the Instant Client feature

This guide does not describe how to install the Custom installation type.

Where to Get Additional Installation Information

For more detailed information about installing Oracle Database Client, refer to *Oracle Database Client Installation Guide for hp-ux PA-RISC (64-Bit)*.

This guide is available on the product disc. To access it, use a Web browser to open the `welcome.htm` file located in the top-level directory of the installation media, and then select the **Documentation** tab.

Logging In to the System as root

Before you install Oracle Database Client, you must complete several tasks as the `root` user. To log in as the `root` user, complete one of the following procedures:

Note: You must install the software from an X Window System workstation, an X terminal, or a PC or other system with X server software installed.

- If you are installing the software from an X Window System workstation or X terminal, then:
 1. Start a local terminal session, for example, an X terminal (`xterm`).
 2. If you are not installing the software on the local system, then enter the following command to enable the remote host to display X applications on the local X server:

```
$ xhost fully_qualified_remote_host_name
```

For example:

```
$ xhost somehost.us.acme.com
```

3. If you are not installing the software on the local system, then use the `ssh`, `rlogin`, or `telnet` command to connect to the system where you want to install the software:

```
$ telnet fully_qualified_remote_host_name
```

4. If you are not logged in as the `root` user, then enter the following command to switch user to `root`:

```
$ su - root  
password:  
#
```

- If you are installing the software from a PC or other system with X server software installed, then:

Note: If necessary, refer to your X server documentation for more information about completing this procedure. Depending on the X server software that you are using, you may need to complete the tasks in a different order.

1. Start the X server software.
2. Configure the security settings of the X server software to permit remote hosts to display X applications on the local system.
3. Connect to the remote system where you want to install the software and start a terminal session on that system, for example, an X terminal (`xterm`).
4. If you are not logged in as the `root` user on the remote system, then enter the following command to switch user to `root`:

```
$ su - root
password:
#
```

Checking the Hardware Requirements

The system must meet the following minimum hardware requirements:

- 256 MB of physical RAM
- The following table gives the swap space requirement in terms of available RAM.

Available RAM	Swap Space Required
Up to 256 MB	3 times the size of RAM
Between 257 MB and 512 MB	2 times the size of RAM
Between 513 MB and 726 MB	1.5 times the size of RAM
More than 726 MB	0.75 times the size of RAM

- The minimum client installation `TEMP` space required is 115 MB. The minimum disk space requirement in the `/tmp` directory depends on the installation type you have selected. The following table lists the minimum disk space requirements for the `/tmp` directory in each type of installation.

Installation Type	Disk Space Required for the /tmp Directory (MB)
Instant	120
Admin	835
Runtime	470
Custom (all components selected)	765

- Between 150 MB and 1.5 GB of disk space for the Oracle software, depending on the installation type

To ensure that the system meets these requirements, follow these steps:

1. To determine the physical RAM size, enter the following command:

```
# grep "Physical:" /var/adm/syslog/syslog.log
```

If the size of the physical RAM installed in the system is less than the specified value, then you must install more memory before continuing.

2. To determine the size of the configured swap space, enter the following command:

```
# /usr/sbin/swapinfo -a
```

If necessary, refer to your operating system documentation for information about how to configure additional swap space.

3. To determine the amount of free disk space available in the `/tmp` directory, enter the following command:

```
# bdf /tmp
```

If there is less than 400 MB of disk space available in the `/tmp` directory, then complete one of the following steps:

- Delete unnecessary files from the `/tmp` directory to meet the disk space requirement.
 - Set the `TEMP` and `TMPDIR` environment variables when setting the `oracle` user's environment (described later).
 - Extend the file system that contains the `/tmp` directory. If necessary, contact your system administrator for information about extending file systems.
4. To determine the amount of free disk space available on the system, enter the following command:

```
# bdf
```

This command displays the disk space usage on all mounted file systems. You must identify a file system with sufficient disk space.

The following table shows the approximate disk space requirements for software files for each installation type:

Installation Type	Requirement for Software Files
Instant Client	96 MB
Administrator	1.9 GB
Runtime	1.5 GB
Custom (maximum)	2.0 GB

5. To determine whether the system architecture can run the software, enter the following command:

```
# /bin/getconf KERNEL_BITS
```

This command should return the following output:

```
64
```

If you do not see the expected output, then you cannot install the software on this system.

Checking the Software Requirements

The system must meet the following minimum software requirements.

- The operating system version must be HP-UX 11i V1 (11.11) PA-RISC or HP-UX 11i V2 (11.23).

For the Oracle products that you want to install, the system must meet the following product-specific requirements:

- Oracle Messaging Gateway

This product supports the integration of Oracle Streams Advanced Queuing (AQ) with the following software:

- IBM WebSphere MQ V5.3, client and server:

```
MQSERIES.MQM-CL-HPUX  
MQSERIES.MQM-SERVER
```

- TIBCO Rendezvous 7.2

- PL/SQL native compilation, Pro*C/C++, Oracle Call Interface, Oracle C++ Call Interface, and Oracle XML Developer's Kit (XDK)

HP C Compiler (B.11.11.12)

HP aC++ Compiler (aCC A.03.60)

GCC compiler gcc 3.4.0 (64-Bit) for 11i V1 and 11i V2

Note: The gcc compiler is supported only for PL/SQL native compilation.

- Oracle JDBC/OCI Drivers

You can use the following optional Java SDK versions with the Oracle JDBC/OCI drivers, however they are not required for the installation:

- Java SDK 1.3.1.16 with the JNDI extension
- Java SDK 1.2.2.09
- Java SDK 1.4.2.08
- Java SDK 5.0

Note: Java SDK 1.4.2 is installed with this release.

To ensure that the system meets these requirements:

1. To determine which version of the operating system is installed, enter the following command:

```
# uname -a
```

```
HP-UX hostname B.11.11 U 9000/800 109444686  
unlimited-user license
```

In this example, the version of HP-UX 11i is 11.11.

2. To determine whether a bundle, product, or fileset is installed, enter a command similar to the following, where *level* is bundle, product, or fileset:

```
# /usr/sbin/swlist -l level | more
```

If a required bundle, product, or fileset is not installed, then you must install it. Refer to your operating system or software documentation for information about installing products.

In addition, you need to verify that the following patches are installed on the system.

Note: There may be more recent versions of the patches listed installed on the system. If a listed patch is not installed, then determine whether a more recent version is installed before installing the version listed.

- For all installations on HP-UX, the following patches are required:

Quality Pack bundle:

HP-UX 11i Quality Pack (GOLDQPK11i), Dec 2004 or later:
GOLDQPK11i

Patches for HP-UX 11i V1 (11.11):

- PHNE_31097: ONC/NFS general release/performance patch
- PHSS_31221: HP aC++ -AA runtime libraries (aCC A.03.60)

Patches for HP-UX 11i V2 (11.23):

- PHSS_31849: linker + fdp cumulative patch
- PHSS_31852: aC++ Runtime (PA A.03.61)

None currently required

Patches for JDK on HP-UX 11i (11.11):

PHSS_30970: ld(1) and linker tools cumulative patch

Note: Refer to the following Web site for information about additional patches that may be required by JDK 1.4.2:

<http://www.hp.com/products1/unix/java/patches/index.html>

- For PL/SQL native compilation and installation of Pro*C/C++, Oracle Call Interface, Oracle C++ Call Interface, or Oracle XML Developer's Kit (XDK), the following patches are required:

Patches for HP-UX 11i V1 (11.11):

- PHSS_32508: HP aC++ Compiler (A.03.63)
- PHSS_32509: ANSI C compiler B.11.11.12 cumulative patch
- PHSS_32510: +O4/PBO Compiler B.11.11.12 cumulative patch

Patches for HP-UX 11i v2 (11.23):

- PHSS_32511: HP aC++ Compiler (A.03.63)
- PHSS_32512: ANSI C compiler B.11.11.12 cumulative patch

- PHSS_32513: +O4/PBO Compiler B.11.11.12 cumulative patch
- PHSS_29655: aC++ Compiler (A.05.52)
- PHSS_29656: HP C Compiler (A.05.52)
- PHSS_29657: u2comp/be/plugin library Patch
- For Oracle Messaging Gateway installation, the following corrective service diskettes (CSDs) for WebSphere MQ are required:

CSD05 or later for WebSphere MQ V5.3

To ensure that the system meets these requirements:

1. On PA-RISC systems only, enter the following command to determine whether the HP-UX 11i Quality Pack is installed:

```
# /usr/sbin/swlist -l bundle | grep GOLD
```

If the Quality Pack is not installed or if the date is before June 2003, then download the latest Quality Pack from the following Web site and install it:

http://www.hp.com/go/softwareinfo/SUPPORT_PLUS

2. To determine whether a patch is installed, enter a command similar to the following:

```
# /usr/sbin/swlist -l patch | grep PHSS_28880
```

Alternatively, to list all installed patches, enter the following command:

```
# /usr/sbin/swlist -l patch | more
```

If a required patch is not installed, then download it from the following Web site and install it:

<http://itresourcecenter.hp.com>

If the Web site shows a more recent version of the patch, then download and install that version.

Creating Required Operating System Group and User

The following local operating system group and user must exist on the system:

- The Oracle Inventory group (`oinstall`)
- The Oracle software owner (`oracle`)

To determine if this group and user already exist, and if required, to create them, follow these steps:

1. To determine if the `oinstall` group exists, enter the following command:

```
# more /var/opt/oracle/oraInst.loc
```

If the output of this command shows the `oinstall` group name, then the group already exists.

If the `oraInst.loc` file exists, then the output from this command is similar to the following:

```
inventory_loc=/u01/app/oracle/oraInventory  
inst_group=oinstall
```

The `inst_group` parameter shows the name of the Oracle Inventory group (`oinstall`).

2. If necessary, enter the following command to create the `oinstall` group:

```
# /usr/sbin/groupadd oinstall
```

3. To determine whether the `oracle` user exists and belongs to the correct groups, enter the following command:

```
# id oracle
```

If the `oracle` user exists, then this command displays information about the groups to which the user belongs. The output should be similar to the following, indicating that `oinstall` is the primary group:

```
uid=440(oracle) gid=200(oinstall)
groups=201(dba),202(oper)
```

4. If necessary, complete one of the following actions:

- If the `oracle` user exists, but its primary group is not `oinstall`, then enter a command similar to the following, where the `-g` option specifies `oinstall` as the primary group and the `-G` option specifies any existing groups to which the `oracle` user belongs:

```
# /usr/sbin/usermod -g oinstall -G dba oracle
```

- If the `oracle` user does not exist, then enter the following command to create it:

```
# /usr/sbin/useradd -g oinstall [-G dba] oracle
```

This command creates the `oracle` user and specifies:

oinstall as the primary group

dba as an optional secondary group

5. Enter the following command to set the password of the oracle user:

```
# passwd oracle
```

Creating an Oracle Base Directory

Create an Oracle base directory with a name similar to the following, and specify the correct owner, group, and permissions for it:

```
/u01/app/oracle
```

The Optimal Flexible Architecture (OFA) guidelines recommend that you use a path similar to the following for the Oracle base directory:

```
/mount_point/app/oracle_sw_owner
```

To determine where to create this directory:

1. Enter the following command to display information about all mounted file systems:

```
# bdf
```

This command displays information about all of the file systems mounted on the system, including:

- The physical device name
 - The total amount, used amount, and available amount of disk space
 - The mount point directory for that file system
2. From the display, identify a file system that has sufficient disk space.
 3. Note the name of the mount point directory for the file system that you identified.

To create the required directory and specify the correct owner, group, and permissions for it, follow these steps:

Note: In the following procedure, replace /u01 with the appropriate mount point directory that you identified in Step 3 previously.

1. Enter the following command to create subdirectories in the mount point directory that you identified for the Oracle base directory:

```
# mkdir -p /u01/app/oracle
```

2. Change the owner and group of the directory that you created to the `oracle` user and the `oinstall` group:

```
# chown -R oracle:oinstall /u01/app/oracle
```

3. Change the permissions on the directory that you created to 775:

```
# chmod -R 775 /u01/app/oracle
```

When you configure the oracle user's environment later during the installation, set the `ORACLE_BASE` environment variable to specify the Oracle base directory that you have created.

Configuring the oracle User's Environment

You run Oracle Universal Installer from the `oracle` account. However, before you start Oracle Universal Installer, you must

configure the environment of the `oracle` user. To configure the environment, you must:

- Set the default file mode creation mask (`umask`) to `022` in the shell startup file.
- Set the `DISPLAY` environment variable.

To set the `oracle` user's environment:

1. Start a new terminal session, for example, an X terminal (`xterm`).
2. Enter the following command to ensure that X Window applications can display on this system:

```
$ xhost fully_qualified_remote_host_name
```

3. Complete one of the following steps:
 - If the terminal session is not connected to the system where you want to install the software, then log in to that system as the `oracle` user.
 - If the terminal session is connected to the system where you want to install the software, then switch user to `oracle`:

```
$ su - oracle
```

4. To determine the default shell for the `oracle` user, enter the following command:

```
$ echo $SHELL
```

5. Open the `oracle` user's shell startup file in any text editor:

- C shell (`csh` or `tcsh`):

```
% vi .login
```

6. Enter or edit the following line in the shell startup file, specifying a value of `022` for the default file mode creation mask:

```
umask 022
```

7. If the `ORACLE_SID`, `ORACLE_HOME`, or `ORACLE_BASE` environment variable is set in the file, then remove the corresponding lines from the file.
8. Save the file, and exit from the editor.
9. To run the shell startup script, enter the following command:

- Bash shell:

```
$ . ~/.bash_profile
```

- Bourne shell, or Korn shell:

```
$ . ~/.profile
```

- C shell:

```
% source ~/.login
```

10. If you determined that the `/tmp` directory has less than 400 MB of free disk space, then identify a file system with at least 400 MB of free space and set the `TEMP` and `TMPDIR` environment variables to specify a temporary directory on this file system:

- a. Use the `bdf` command to identify a suitable file system with sufficient free space.
- b. If necessary, enter commands similar to the following to create a temporary directory on the file system that you identified, and set the appropriate permissions on the directory:

```
$ su - root  
# mkdir /mount_point/tmp  
# chmod a+wr /mount_point/tmp
```

```
# exit
```

- c. Enter commands similar to the following to set the `TEMP` and `TMPDIR` environment variables:

Bourne, Bash, or Korn shell:

```
$ TEMP=/mount_point/tmp  
$ TMPDIR=/mount_point/tmp  
$ export TEMP TMPDIR
```

C shell:

```
% setenv TEMP /mount_point/tmp  
% setenv TMPDIR /mount_point/tmp
```

11. If you are not installing the software on the local system, then enter a command similar to the following to direct X applications to display on the local system:

- Bourne, Bash, or Korn shell:

```
$ DISPLAY=local_host:0.0 ; export DISPLAY
```

- C shell:

```
% setenv DISPLAY local_host:0.0
```

In this example, *local_host* is the host name or IP address of the system that you want to use to display Oracle Universal Installer (your workstation or PC).

12. Enter commands similar to the following to set the `ORACLE_BASE` environment variable:

- Bourne, Bash, or Korn shell:

```
$ ORACLE_BASE=/u01/app/oracle
```

- C shell:

```
% setenv ORACLE_BASE /u01/app/oracle
```

In these examples, `/u01/app/oracle` is the Oracle base directory that you created earlier.

13. Enter the following commands to ensure that the `ORACLE_HOME` and `TNS_ADMIN` environment variables are not set:

- Bourne, Bash, or Korn shell:

```
$ unset ORACLE_HOME
```

```
$ unset TNS_ADMIN
```

- C shell:

```
% unsetenv ORACLE_HOME
% unsetenv TNS_ADMIN
```

14. To verify that the environment has been set correctly, enter the following commands:

```
$ umask
$ env | more
```

Verify that the `umask` command displays a value of `22`, `022`, or `0022` and the environment variables that you set in this section have the correct values.

Mounting the Product Disc

On most HP-UX systems, the product disc mounts automatically when you insert it into the drive. If the disc does not mount automatically, follow these steps to mount it:

1. Switch user to root:

```
$ su - root
```

2. If necessary, enter a command similar to the following to eject the currently mounted disc, then remove it from the drive:

```
# /usr/sbin/umount /SD_DVD
```

In this example, `/SD_DVD` is the mount point directory for the disc drive.

3. Insert the disc into the disc drive, then enter a command similar to the following to mount it:

```
# /usr/sbin/mount -F cdfs -o rr /dev/dsk/cxytzy /SD_DVD
```

In this example, `/SD_DVD` is the disc mount point directory and `/dev/dsk/cxytzy` is the device name for the disc device, for example `/dev/dsk/c0t2d0`.

4. If Oracle Universal Installer displays the Disk Location dialog box, enter the disc mount point directory path, for example:

```
/SD_DVD
```

Installing Oracle Database Client

After configuring the `oracle` user's environment, start Oracle Universal Installer and install the Oracle software as follows:

1. To start Oracle Universal Installer, complete one of the following steps depending on the location of the installation files:
 - If the installation files are on disc, enter commands similar to the following, where `directory_path` is the path of the `db` directory on the DVD:

```
$ cd /tmp
$ /directory_path/runInstaller
```

- If the installation files are on the hard disk, change directory to the `db` directory and enter the following command:

```
$ ./runInstaller
```

If Oracle Universal Installer does not start, then refer to *Oracle Database Client Installation Guide for hp-ux PA-RISC (64-Bit)* for information about how to troubleshoot X display problems.

2. The following table describes the recommended action for each Oracle Universal Installer screen. Use the following guidelines to complete the installation:

- If you need more assistance, or if you want to choose an option that is not a default, then click **Help** for additional information.
- If you encounter errors while installing or linking the software, then refer to *Oracle Database Client Installation Guide for hp-ux PA-RISC (64-Bit)* for information about troubleshooting.

Note: If you have completed the tasks listed previously, then you can complete the installation by choosing the default values on most screens.

Screen	Recommended Action
Select Installation Method	The Basic Installation option is selected by default. Specify the directory path of the Oracle home. Ensure that the UNIX DBA group <code>oinstall</code> is selected. If you want to create a starter database, then specify a name and password for it. Then, click Next .

Screen	Recommended Action
Specify Inventory Directory and Credentials	<p>This screen is displayed only during the first installation of Oracle products on a system.</p> <p>Specify the full path of the Oracle Inventory directory. Ensure that the operating system group selected is <code>oinstall</code>. Then, click Next.</p>
Product-Specific Prerequisite Checks	<p>Verify that all of the prerequisite checks succeed, then click Next.</p> <p>Oracle Universal Installer checks the system to verify that it is configured correctly to run Oracle software. If you have completed all of the preinstallation steps in this guide, all of the checks should pass.</p> <p>If a check fails, then review the cause of the failure listed for that check on the screen. If possible, rectify the problem and rerun the check. Alternatively, if you are satisfied that your system meets the requirements, then you can select the check box for the failed check to manually verify the requirement.</p>
Summary	<p>Review the information displayed on this screen, and then click Install.</p>
Install	<p>This screen displays status information while the product is being installed.</p>

Screen	Recommended Action
Configuration Assistants	This screen displays status information for the configuration assistants that configure the software and create a database. When the message is displayed at the end of this process, click OK to continue.
Execute Configuration Scripts	When prompted, read the instructions and then run the scripts mentioned on this screen. Click OK to continue.
End of Installation	<p>The configuration assistants configure several Web-based applications, including Oracle Enterprise Manager Database Control. This screen displays the URLs configured for these applications. Make a note of the URLs used. The port numbers used in these URLs are also recorded in the following file:</p> <pre><i>oracle_home/install/portlist.ini</i></pre> <p>To exit from Oracle Universal Installer, click Exit and then click Yes.</p>

What to Do Next?

After you have successfully installed Oracle Client, refer to *Oracle Database Client Installation Guide for hp-ux PA-RISC (64-Bit)* for information about required and optional postinstallation steps.

Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible, with good usability, to the disabled community. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Accessibility standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be accessible to all of our customers. For more information, visit the Oracle Accessibility Program Web site at

<http://www.oracle.com/accessibility/>

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

TTY Access to Oracle Support Services

Oracle provides dedicated Text Telephone (TTY) access to Oracle Support Services within the United States of America 24 hours a day, seven days a week. For TTY support, call 800.446.2398.

